

Easergy Studio V9.2.1 Release Notes

Document date: 19 October 2020
Version: B

Schneider Electric Industries SAS

Postal address / Adresse postale :
Site TECHNOPOLE
28 rue Henri Tarze
38050 Grenoble Cedex 9
Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
Société par actions simplifiée au capital de 928.298.512 euros
954 503 439 rcs Nanterre – code APE : 2712Z
Siret : 954 503 439 01719
n° ident. TVA : FR 04 954 503 439
Siège social : 35, rue Joseph Monier
F – 92500 Rueil-Malmaison

1 How to get Easergy Studio Installer?

To get the Easergy Studio Installer, go to www.se.com or use Schneider Electric Software update to be inform of new releases and download automatically.

2 About release V9.2.1

This release provides a full installation of Schneider-Electric Easergy Studio V9.2.1.

- Its supersets version V9.2.0 and oldest.
- Please at installation, use update option of Easergy Studio installer.
- Or remove any previous version of Easergy Studio (do not remove the data models)
- Your database and systems will not be removed.
- Install afterwards Easergy Studio V9.2.1.

3 How to install

This installation

- is to be downloaded to your hard disk for later installation by running the .exe file
- is providing an installation shield for a most convenient upgrade of your Easergy Studio
- retains all existing systems (or projects)
- can be run multiple times

4 Windows compatibility

This Easergy Studio is compatible with Windows 10.

5 Known issue

5.1 Language installation

Mandatory to install English version in addition to another language file Germany, Portuguese, Spanish, etc. After, the user can switch to his preferred language.

Schneider Electric Industries SAS

Postal address / Adresse postale :
Site TECHNOPOLE
28 rue Henri Tarze
38050 Grenoble Cedex 9
Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
Société par actions simplifiée au capital de 928.298.512 euros
954 503 439 rcs Nanterre – code APE : 2712Z
Siret : 954 503 439 01719
n° ident. TVA : FR 04 954 503 439
Siège social : 35, rue Joseph Monier
F – 92500 Rueil-Malmaison

7 Computer characteristics (for information)

Minimum and recommended hardware requirements for Easergy Studio and other tools included UPCT, P746 RHMI, P740 Topology Tool are based on all tools included in current installation package.

The results are based on Easergy Studio v9.2.1 requirements.

7.1 Minimum Requirements:

Platform	Processor	RAM	HDD ¹	HDD ²
Windows 10 x86	1 GHz	1 GB	900 MB	2,1 GB
Windows 10 x64	1 GHz	1 GB	900 MB	2,1 GB

7.2 Recommended Requirements:

Platform	Processor	RAM	HDD ³	HDD ⁴
Windows 10 x86	1 GHz	2 GB	900 MB	2,1 GB
Windows 10 x64	1 GHz	2 GB	900 MB	2,1 GB

Notes:

1. Both configurations do not include Data Models HDD requirements.
2. Screen resolution for minimum requirements: Super VGA (800 x 600).
3. Screen resolution for recommended requirements: XGA (1024x768) and higher.
4. Easergy Studio must be started with Administrator privileges.

¹ OS with Windows Updates updated on 2015/05

² OS without Windows Updates installed

³ OS with Windows Updates updated on 2015/05

⁴ OS without Windows Updates installed

Schneider Electric Industries SAS

Postal address / Adresse postale :
 Site TECHNOPOLE
 28 rue Henri Tarze
 38050 Grenoble Cedex 9
 Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
 Société par actions simplifiée au capital de 928.298.512 euros
 954 503 439 rcs Nanterre – code APE : 2712Z
 Siret : 954 503 439 01719
 n° ident. TVA : FR 04 954 503 439
 Siège social : 35, rue Joseph Monier
 F – 92500 Rueil-Malmaison

9 New features

9.1 Release V9.2.1


9.1.1 Command Line Tool to Transfer Easergy Micom P40 Data

Added new enhancement to extract events and disturbances from Micom P40 series.

9.2 Release V9.2.0

9.2.1 Template manager

Template management enables users to perform massive change propagation inside Studio System. Template device is a new kind of element in Studio System – it mimics regular device in the way that it



allows to store and edit configuration files but it has all online functionality like Send, Extract, Disturbance Records, Measurements etc. removed. Template Device is a virtual device that has one or more parts of its files or complete files tagged as template. Template tagged part of a file is a part that can be propagated to other files with same type and same product reference. As templates are virtual devices which are part of the system (as well as any other device). They can be imported and exported as system elements. They can also be created from a physical device (physical device can be copied as a template)

A template device has the list of devices linked to it. This list can be edited in a specific window in which user can select or unselect which one of matching devices refers to the template.

Template files “marked as default” (source) are propagated to linked devices files “marked as default” of the same type (target).

9.2.2 Command Line Tool to Transfer Easergy Micom P40 Data

The command line makes possible for a user to extract Easergy Micom P40 settings file, events and disturbances record with a command line. Additionally, it is also possible to send settings file to IED. All operations with support for Cyber Security passwords.

9.2.3 Integration of Easergy Pro for Easergy P3 and Easergy P5 devices into Easergy Studio

Added possibility to manager all files from Easergy P3, Easergy P5, Micom P10, MiCOM P20, Easergy Micom P30 and Easergy Micom P40 in to “Studio Explorer” project view.

Added possibility to create / open the off-line settings file from Easergy P3 and Easergy P5 devices.

Added possibility to create “Connections” into Studio Explorer.

Added possibility to save manually all Disturbance Records files into “Studio Explorer” project view.

9.2.4 User preferences – Enable/disable Safe Repository

The user can enable or disable from user preferences the option for Schneider Electric Safe Repository cloud.

Schneider Electric Industries SAS

Postal address / Adresse postale :
Site TECHNOPOLE
28 rue Henri Tarze
38050 Grenoble Cedex 9
Tel. +33 (0)4 76 57 60 60

<http://www.se.com>


Legal information / Mentions légales
Société par actions simplifiée au capital de 928.298.512 euros
954 503 439 rcs Nanterre – code APE : 2712Z
Siret : 954 503 439 01719
n° ident. TVA : FR 04 954 503 439
Siège social : 35, rue Joseph Monier
F – 92500 Rueil-Malmaison

9.2.5 New Data Model Server

For Cyber Security reason, the server of Easergy Micom device Data Models was updated. All the users using Easergy Studio before version 9.0.0 should update to the newest release.


9.2.6 Export Multiple MCL/CID files

The user can export one of multiples MCL/CID files in the single operation.



9.2.7 Convert Multiple Settings Files

The user can convert multiples settings files to different software version in a single operation.



9.2.8 Access point configuration for Process Bus

The IED Configurator is enabled to manage the choice of access point for Process Bus projects.

9.2.9 Performance Issues

This release also corrects some performance and other issues.

Schneider Electric Industries SAS

Postal address / Adresse postale :
Site TECHNOPOLE
28 rue Henri Tarze
38050 Grenoble Cedex 9
Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
Société par actions simplifiée au capital de 928.298.512 euros
954 503 439 rcs Nanterre – code APE : 2712Z
Siret : 954 503 439 01719
n° ident. TVA : FR 04 954 503 439
Siège social : 35, rue Joseph Monier
F – 92500 Rueil-Malmaison

10 Enhancement and Corrected issues

10.1 Release V9.2.1

- # 6702 Corrected, MCL and CID banks to be switched with Easergy Studio and Easergy Transfer Tool
- # 6722 Corrected, MU to be available in Sample Value Subscribing if its Identifier does not match the the rules
- # 6705 Corrected, Save SCL failed when use FPN to map virtual IED (without PB) to physical IED (with PB)
- # 6720 Corrected, Failed to attach label to input or output in PSL
- # 6703 Corrected, create mcl for device operating in IEC61850 Ed.1
- # 6700 Corrected, Save SCL failed with four report clients
- # 6691 Corrected, Temporary false positive when validating a cid after scd import
- # 6679 Enhancement on Texts in DEV/IO Config dialog
- # 6575 Enhancement on New assembly variants from C434-661 84T in BTC V3.3.0
- # 6653 Corrected, MCL upgrade
- # 6617 Corrected, Deactivation of function groups Px30
- # 6708 Corrected, Report Control Blocks: validation when Access Point in Report Clients is empty
- # 6707 Corrected, Limited Function Copy/Paste
- # 6682 Corrected, User Defined Bay type is changed to Standard for BTC opened from BBT
- # 5656 Corrected, BTC - Menu "Edit/Reserved Areas"
- # 6685 Corrected, Background color is stored only for Switchgear Units in BBT
- # 6673 Corrected, Last character cut-off for some signals in exported HDR file
- # 6612 Corrected, Warning messages
- # 6696 Enhancement on Easergy Transfer Tool to inform that there are less Disturbance Records on the relay side than expected amount to be extracted
- # 6674 Enhancement on "Created by" field added to exported HDR file
- # 6130 Corrected, Copy selection
- # 6681 Corrected, BBT device allocate in files
- # 6689 Corrected, Progress bar for Disturbance Records extraction
- # 6677 Corrected, Unmap button in Goose Subscribing

10.2 Release V9.2.0 / V9.1.0 / V9.0.0 / V8.2.0 / V8.0.1

- # 3957 Changing Modbus setting value by MiCOM S1 Studio always marks as modified.
- # 4095 Corrected error occurred when add data model in DMM under hardened Win 7 OS
- # 4600 Corrected error to send Customized Files to Px30 extended platform device via SFTP
- # 4668 Corrected DMM - application is case sensitive - SDMA file with capital letters extension will be reported as invalid
- # 4783 Corrected MS1S stops responding on Px30 device settings extraction when connection response time parameter is set to low value
- # 4846 Enhancement on Px40 PSL Editor CS 3 - proper communication error handling
- # 4990 Corrected Firmware issue - FPN firmware accepts the normal Px4x template and download is successful
- # 5082 Corrected a IEDConfigurator does not download MCL-files.
- # 5403 Enhancement on DMM - Missing marquee while reading Index file on startup
- # 5412 Enhancement on ED2 & FPN store project before switch to IED Configurator
- # 5658 Enhancement on FPN: SCD Update
- # 5659 Corrected FPN : Mapping to unknown LNTYPE
- # 5660 Corrected IFPN: ICD generation
- # 5663 Corrected FPN : mapping shall be allowed if CDC match
- # 5756 Enhancement on Import Excel Template - Symbols of units are not displayed properly in Logs
- # 5785 Enhancement on Event Viewer shows warning messages after changing language of Studio System
- # 5823 Corrected Configuration data(Application ID and Configuration Revision) can not be saved in MCL file
- # 5840 Enhancement on Disturbance Record name with date format as YY.MM.DD hh.mm.ss
- # 5845 Enhancement on Installing data models from Internet sources
- # 5859 Enhancement on Decrease DNP Max client from 8 to 6 for dnp set file
- # 5867 Enhancement on shortcuts to quickly send/extract selected settings cells and groups

Schneider Electric Industries SAS

Postal address / Adresse postale :
 Site TECHNOPOLE
 28 rue Henri Tarze
 38050 Grenoble Cedex 9
 Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
 Société par actions simplifiée au capital de 928.298.512 euros
 954 503 439 rcs Nanterre – code APE : 2712Z
 Siret : 954 503 439 01719
 n° ident. TVA : FR 04 954 503 439
 Siège social : 35, rue Joseph Monier
 F – 92500 Rueil-Malmaison

- # 5869 Enhancement on reading index from Internet sources
- # 5878 Useless Change Configuration Template menu item in edition 2
- # 5887 Enhancement on Increase Ping time out for Ethernet connexion from 120ms to 1000ms
- # 5888 Using 'Connect' on Px30 connection is set as default
- # 5889 Enhancement on Installing Microsoft .NET Framework 4.7.1
- # 5892 Enhancement on Switching from Serial to Ethernet connection for Px30 display 'ignore timer' dialog
- # 5896 Enhancement to 'Extract all records' for a Px30 devices require adding new comment during whole extraction process
- # 5899 Send Firmware option removed from Px30 context menu
- # 5915 Enhancement, added a Checkbox/button to select all checkboxes in Send to Safe Repository and Browse Safe Repository
- # 5926 Enhancement, Print preview - selected node show all cells inside
- # 5928 Enhancement, Remove "Use fixed incoming TCP port" section for Px30 with firmware below -660
- # 5929 Enhancement, Operating Data Records and Monitoring Signal Records data format improved
- # 5935 Enhancement, Arrows in ES consistency
- # 5936 Enhancement, Process vbus - Changed the up-down button to the drop-down list
- # 5938 Enhancement, Add an option to display IED like a list rather than like small icon in "Import SCD"
- # 5941 Enhancement, New column with version of file available on asset store added to list of elements in Send to Safe Repository dialog
- # 5942 Enhancement, New columns with buttons to increase minor or major version added to list of elements in Send to Safe Repository dialog
- # 5946 Enhancement, Added 'Ignore ID' checkbox to Diagram Compare Results dialog in PSL Editor
- # 5947 Enhancement, Added the physical IO reference
- # 5950 Enhancement, Messages in "Downloading Safe Repository files" dialog improved
- # 5955 Enhancement, Log messages during Safe Repository operations display 'Serial Number'/'Product Number'
- # 5961 Corrected, Easergy Studio 8.0.0 with Patch does not download CID file
- # 5963 Corrected, Network Connection with Easergy Studio
- # 5964 Enhancement, Apply template - Added possibility to choose another SCD file than the one from FPN project
- # 5968 Corrected, Goose Subscription - Data type = "BSTR2" in V8.0.0.0 is changed into "SPS" if opened in V7.1.0
- # 5977 Enhancement, 'Select All' checkbox selected always when all files are selected
- # 5995 Enhancement, added possible to configure ScIMng transformations from UI
- # 6000 Enhancement, Notice how to configure datasets for Process Bus removed
- # 6004 Enhancement, Verify option only available when CID file not match device
- # 6005 Enhancement, P138: fPN_IEDC tool did not support adding additional LD
- # 6010 Enhancement, Swap Safe Repository no longer visible
- # 6025 Enhancement, Cursor in blank field of Easergy Studio Diagnostic Tool is redundant
- # 6028 Enhancement, Added tooltips and modify Interface labels in Communication tab
- # 6056 Enhancement, In setting conversion
- # 6059 Enhancement, Added "Delete System" button to Easergy Studio Start Page
- # 6069 Enhancement, Implement Easergy P1V1 and P1F1 compatibility with ES
- # 6077 Corrected, Exception while QC - 'Busy holdoff time (ms)' has value greater than 32767
- # 6093 Enhancement, 'Copy selection' - applied selected branch does not copy all elements belonging (only node)
- # 6094 Enhancement, 'Copy selection' copy all list parameters for multiselect cells
- # 6100 Enhancement on 'Display borders' checkbox state at BTC Tools
- # 6133 Enhancement, Map DOs dialog as resizable
- # 6134 Enhancement, Removed from 'Add Existing File' *.hex extension (BTC folder)
- # 6135 Enhancement, Not linked DOs in Map DOs dialog is highlighted
- # 6147 Enhancement, added send BTC files to Px30 device without manual conversion to BBT file
- # 6148 Enhancement, removed required for User Symbol (including <Text> element) to have at least one Data Point assigned in BTC.
- # 6149 Enhancement, User is able to add elements to already selected elements using shift button and drag mouse cursor over the area with new elements on BTC
- # 6155 Enhancement, Change Date and Time dialog in Supervise Device is reading actual date and time from the relay
- # 6164 Enhancement, 'Created by' field in extracted Px30 log files is improved

Schneider Electric Industries SAS

Postal address / Adresse postale :
 Site TECHNOPOLE
 28 rue Henri Tarze
 38050 Grenoble Cedex 9
 Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
 Société par actions simplifiée au capital de 928.298.512 euros
 954 503 439 rcs Nanterre – code APE : 2712Z
 Siret : 954 503 439 01719
 n° ident. TVA : FR 04 954 503 439
 Siège social : 35, rue Joseph Monier
 F – 92500 Rueil-Malmaison

- # 6186 Enhancement, File extensions related to Binary Type Configuration format added in Studio as Binary Template Configuration
- # 6187 Enhancement, Highlight unassigned elements on the diagram on simulation tab on BTC
- # 6195 Enhancement, State labels for Switchgear Units with only 2 states is improved
- # 6196 Enhancement, Added Change SCD button to Apply Template dialog
- # 6197 Enhancement, IED Configurator is asking if user wants to overwrite the file if SCD was changed in opened FPN project
- # 6198 Corrected stability of comparing PSL files
- # 6200 Enhancement, Ohm (omega) and Celsius units is modified on Simulation tab in the BTC
- # 6202 Enhancement, Fct. Assignm. U elements from INP settings group and Fct. Assignm. K elements from OUP settings group is available on the Data Points list on BTC
- # 6242 Corrected, Overwriting of parameters of an IED with a setting file with a different F Number
- # 6251 Enhancement, P30 - Disturbance record for railway - Change frequency from "16" to "16.7"
- # 6263 Enhancement, MiCOM S30 is removed from the Open Default Settings file protocol list
- # 6270 Enhancement, Improve time of extracting help's files during installation ES
- # 6277 Enhancement, Event report list - added line stating Easergy Studio "Connection" setting used
- # 6278 Enhancement, Event report list - date format DD.MM.YYYY for German
- # 6290 Corrected, Definition 003.235 COMM1 Ind./cl. analog inp. class configuration
- # 6294 Enhancement, Studio installer "hangs up" during Studio upgrade
- # 6304 Enhancement, S1 RDF simplify S1 data model files
- # 6308 Enhancement, Export Devices List is upgraded for Px30 relays
- # 6314 Enhancement, Copy and Paste parameters between different Px30 devices is available
- # 6315 Enhancement, Paste parameters by address is added to Studio explorer context menu
- # 6343 Corrected, ES V8.2.0 Connect/Quick connect and Connect/Scan network improvements in German
- # 6378 Enhancement, new layout of Position of delete and close button
- # 6401 Enhancement, German labels in Log Records header is improved
- # 6418 Enhancement, Only Active Bank is selected for MCL and CID files in Extract All Configurations dialog by default
- # 6419 Corrected, Quality Obj/Elem Index disabled after open the saved CID file.
- # 6420 Enhancement, Easergy Studio is allow to add comment during Disturbance Records extraction
- # 6423 Enhancement, added Comment for each disturbance record before extracting from P/Cx30
- # 6444 Enhancement, Easergy Studio: COMTRADE file name output format yy-mm-dd... by default
- # 6450 Enhancement, Export device list - P30 - Avoid displayed useless 000
- # 6490 Enhancement, Bind button is disabled if there are no devices/templates is bound with
- # 6491 Enhancement, Use case of displaying the Manage Device Binding when there are no matching devices can be upgraded
- # 6508 Enhancement, Both Tag as Template and Untag as Template are enabled
- # 6528 Enhancement, Easergy Transfer Tool is log in console paths to Data Models and Log folders
- # 6531 Enhancement, User choice of selected file types is remembered after propagation
- # 6542 Enhancement, Support for sending slider type cells by Easergy Transfer tool is improved
- # 6566 Corrected, Px2x Setting slow refresh
- # 6589 Enhancement, Created new Dataset is set Location path to System\LLN0 by default
- # 6622 Enhancement, added glasslock while Export MCL/CID Files or Convert Settings Files are invoked
- # 6633 Enhancement, File transfer mode via Ethernet is removed from Px30 Quick Connect and New Connection wizard

Schneider Electric Industries SAS

Postal address / Adresse postale :
 Site TECHNOPOLE
 28 rue Henri Tarze
 38050 Grenoble Cedex 9
 Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
 Société par actions simplifiée au capital de 928.298.512 euros
 954 503 439 rcs Nanterre – code APE : 2712Z
 Siret : 954 503 439 01719
 n° ident. TVA : FR 04 954 503 439
 Siège social : 35, rue Joseph Monier
 F – 92500 Rueil-Malmaison

Schneider Electric Industries SAS

Postal address / Adresse postale :
Site TECHNOPOLE
28 rue Henri Tarze
38050 Grenoble Cedex 9
Tel. +33 (0)4 76 57 60 60

<http://www.se.com>

Legal information / Mentions légales
Société par actions simplifiée au capital de 928.298.512 euros
954 503 439 rcs Nanterre – code APE : 2712Z
Siret : 954 503 439 01719
n° ident. TVA : FR 04 954 503 439
Siège social : 35, rue Joseph Monier
F – 92500 Rueil-Malmaison