

# Release notes

**Product name:** Kerwin

**Version number:** 7.0.3

**Language:** EN



**Date:** 4th October, 2016

**Written by:** Schneider Electric Telecontrol

**Checked by:** Schneider Electric Telecontrol

Toutes les informations contenues dans ce document sont la propriété exclusive de Schneider Electric Telecontrol S.A.S. Elles ne peuvent être divulguées ou utilisées sans notre accord écrit préalable.  
All the information contained in this document is the exclusive property of Schneider Electric Telecontrol S.A.S. It may not be revealed or used without our prior written consent.

**Summary**

|           |  |          |
|-----------|--|----------|
| <b>1.</b> | <b>Introduction .....</b>  | <b>3</b> |
| <b>2.</b> | <b>Description of the version .....</b>  | <b>3</b> |
| <b>3.</b> | <b>Bug tracking list .....</b>   | <b>3</b> |
| 1.1       | #9542 – Case 27259971 - It is possible to modify an object with a empty name/label. ....                                   | 3        |
| 1.2       | #9540 – Case 30206417 - SAUR - Workgroups list must be sorted alphabetically.....  | 3        |
| 1.3       | #9535 – Case 29379570 - SAUR - Labels of variables are not copy when copy/paste a device.....                              | 4        |
| 1.4       | #9543 – Case 27193855 - SAUR - Scrollbar missing when display variables from synoptic.....                                 | 4        |
| 1.5       | #9427 – Case 24073826 - SAUR - Unable to add a variable in an Histo. Misc. file with Kerweb GUI.....                       | 4        |
| 1.6       | #9429 – Case 24780944 - SAUR - Synoptics: 'Read files' action didn't read 'Histo Report' and 'Histo Misc.' type files..... | 4        |
| 1.7       | #9169: Case 13065489 - SAUR - Unlock a site doesn't unlock variables of the site .....                                     | 4        |
| 1.8       | #9290: Case 13392058 - AL KN18449 - Loss for the period of automatic refresh events .....                                  | 4        |
| 1.9       | #9406: Case 16834659 - AL KN18860 - Error when using Yearly program with different years .....                             | 4        |
| 1.10      | #9408: Case 13391014 - AL KN18457 - Variables can be duplicated if the case is different for the name .                    | 4        |
| 1.11      | #9427: Case 24073826 - SAUR - Unable to add a variable in an Histo. Misc. file with Kerweb GUI.....                        | 5        |
| 1.12      | #9428: Case 24422021 - Impossible to delete a BRIO/SP50 device as soon as any SMS action was recorded 5                    | 5        |
| 1.13      | #9517: Visual bug that the word "Periods" is not visible .....   | 5        |
| 1.14      | #9292: Case 15091554 - AL KN18662 - CPU leak in kercom .....   | 5        |
| 1.15      | #9396: Case 21601920 - Netsize SMS are received as SIM SMS.....  | 5        |
| 1.16      | #9379: Case 20520309 - SAUR - Netsize plugin don't work with Windows 2008 .....  | 5        |
| 1.17      | #9515: Case 27278344 - SAUR - Problem with alarms reception with the LACBUS protocole.....                                 | 5        |

Toutes les informations contenues dans ce document sont la propriété exclusive de Schneider Electric Industries S.A.S. Elles ne peuvent être divulguées ou utilisées sans notre accord écrit préalable.  
 All the information contained in this document is the exclusive property of Schneider Electric Industries S.A.S. It may not be revealed or used without our prior written consent.

## 1. Introduction

---

**Document scope**    This document describes the Kerwin version 7.0.3, Kerweb 4.0.3 and Kercom 8.0.3

---

**Application field**    This Kerwin version applies on PC

---

**Comments**    Version 7.0.3 available since 20/10/2016  
Only changes compared to version 7.0.3 are listed below.

---

## 2. Description of the version

The version 7.0.3 fixes some issues. The issues are identified by a “Bug tracker ID”.

## 3. Bug tracking list

### 1.1 #9542 – Case 27259971 - It is possible to modify an object with a empty name/label.

In Kerwin application, warning message is displayed when following fields are empty.

- classes of alarm
- classes of variables
- classes of sites
- site group, users
- categories of files
- categories of variables
- workgroup

Note: Fields other than mentioned above already support warning message for empty field.

### 1.2 #9540 – Case 30206417 - SAUR - Workgroups list must be sorted alphabetically.

In Kerwin application, workgroup list is sorted in alphabetical order in Users dialog box when the user opens workgroup list.

Toutes les informations contenues dans ce document sont la propriété exclusive de Schneider Electric Industries S.A.S. Elles ne peuvent être divulguées ou utilisées sans notre accord écrit préalable.

All the information contained in this document is the exclusive property of Schneider Electric Industries S.A.S. It may not be revealed or used without our prior written consent.

### 1.3 #9535 – Case 29379570 - SAUR - Labels of variables are not copy when copy/paste a device

In Kerwin application, label of the digital input and digital output variable are copied, when, we execute copy/paste action from the site for device (SOFREL).

### 1.4 #9543 – Case 27193855 - SAUR - Scrollbar missing when display variables from synoptic

In Kerweb application, scrollbar is enabled when the variables of a device are displayed from synoptic page.

### 1.5 #9427 – Case 24073826 - SAUR - Unable to add a variable in an Histo. Misc. file with Kerweb GUI

In Kerweb application, we can now add variables in a file of the 'Histo. Misc.' type. Select “None” from Traitement filed when this field is not relevant.

### 1.6 #9429 – Case 24780944 - SAUR - Synoptics: 'Read files' action didn't read 'Histo Report' and 'Histo Misc.' type files

In Kerweb application, 'Read Files' action from synoptics pages reads 'Histo Report' and 'Histo Misc.' type files of a SOFREL device.

### 1.7 #9169: Case 13065489 - SAUR - Unlock a site doesn't unlock variables of the site

When we unlock a site with Kerwin HMI, it unlock's variables of the site.

### 1.8 #9290: Case 13392058 - AL KN18449 - Loss for the period of automatic refresh events

"When a user sets a filter on the types of events and it has an automatic refresh, then the page is displayed correctly and the box "automatic refresh events" momentarily turns red. If the user changes their filter while the box "automatic refresh events" is red (during refresh) while the automatic refresh is interrupted. After correction the box "automatic refresh events" does not turn red and the value of the box does not change.

### 1.9 #9406: Case 16834659 - AL KN18860 - Error when using Yearly program with different years

The changes made in the previous year are retained now. The yearly programs now do not get deleted, even if the changes are made to the other yearly program.

### 1.10 #9408: Case 13391014 - AL KN18457 - Variables can be duplicated if the case is different for the name

When two variables are created with the same name in different cases, the name in Kerwin is always in lower case and the first variable created takes the name <variable name>\_0. That is how it is distinguished and the alarms are also distinguished.

Toutes les informations contenues dans ce document sont la propriété exclusive de Schneider Electric Industries S.A.S. Elles ne peuvent être divulguées ou utilisées sans notre accord écrit préalable.

All the information contained in this document is the exclusive property of Schneider Electric Industries S.A.S. It may not be revealed or used without our prior written consent.

### **1.11 #9427: Case 24073826 - SAUR - Unable to add a variable in an Histo. Misc. file with Kerweb GUI**

In Kerweb GUI we are unable to add a variable in an Histo.Misc.file. Now, the Treatment box has the option 'none' and after selecting 'none', it is possible to add variables in Hist and Misc files.

### **1.12 #9428: Case 24422021 - Impossible to delete a BRIO/SP50 device as soon as any SMS action was recorded**

Now it's possible to delete a BRIO/SP50 device as soon as any SMS action was recorded.

### **1.13 #9517: Visual bug that the word "Periods" is not visible**

While creating a yearly program and saving it, the word "periods" is not visible on the main page of yearly program. After correction the word "periods" is visible on the main page of yearly program.

### **1.14 #9292: Case 15091554 - AL KN18662 - CPU leak in kercom**

In Kercom the CPU leak is occurred and the tasks are not properly released. After correction the CPU leak occurrence is minimized and the tasks are released properly.

### **1.15 #9396: Case 21601920 - Netsize SMS are received as SIM SMS**

After correction It is now possible to set the SMS class in the netsize configuration file. The default SMS class remains 2.

### **1.16 #9379: Case 20520309 - SAUR - Netsize plugin don't work with Windows 2008**

Netsize plugin work with windows 2008. And also when the plugin is correctly registered in registry then launching Kerwin didn't need Administrator access anymore. Administrator access is always needed at first launch of the plugin (or after move the plugin in other folder).

### **1.17 #9515: Case 27278344 - SAUR - Problem with alarms reception with the LACBUS protocole**

When calling sites sofbus there is often failure of protocol research, Kerwin enters LACBUS protocol reception at the SOFBUS, receiving alarms fails. When we remove the receipt of LACBUS protocol calls SOFBUS are OK. IP: Receiving calls LACBUS fails immediately. After correction there is no problem with alarms reception with the LACBUS protocol.